

WL-5460CAM Remote Recording

This document guides you record video from WL-5460CAM to a file server in the local area network.

The IP network in the following example use 210.66.97.0/255.255.255.0 IP subnet.


The IP address of WL-5460CAM is changes to 210.66.97.249.

The IP address of the file server is 210.66.97.246, which is a personal computer with Windows XP operation system.

A folder named **share** is shared for anonymous access in the file folder.

Please refer to the following topology:

Topology:




Note: File server and WL-5460CAM must be in the same IP subnet.

1. Change the IP address of WL-5460CAM. (Change to 210.66.97.249 / 255.255.255.0 in this example)
2. Log in to the web management interface.
3. Enable the motion detection function:
 - 3.1 Browse to ADVANCED → Video → Motion Detection



4. The Video Control Setting shows as following:



- 4.1 Enable the **Motion** check button.
- 4.2 Enable the detection zone check button, give name to each zone (z1, z2, and z3 in this example) and click the **Zone** button.
- 4.3 As the Zone button (Zone1, Zone2 and Zone3) is clicked, the detecting area shows in the video screen. The zone area can be resized by using the mouse.
- 4.4 Adjust the **Sensitivity** and **Percentage** as your wish.
- 4.5 Click **Save** button to save the configuration.
5. Configure the remote recording
 - 5.1 Browse to ADVANCED → Tools → Recording



6. The Remote_Recording menu shows as following:

ADVANCED>> Remote_Recording

None 1
 Upload Image To Network share folder

Login Method: Anonymous
 Login User: *****
 Password: 2

Path: \\210.66.97.246\share 3 4

Shared Folder Mode

None
 Recording File Number: 24 5
 Total Files Sizes: 1000 (MB)

Recording Method

Always
 Schedule
 Day: Mon Tue Wed Thu Fri Sat Sun
 Time Start: 00:00
 Stop: 00:00 6

Smart Recording
 Lengthening Recording Time: 10 sec(s)


7

6.1 Select **Upload Image To Network share folder**

6.2 Choose **Login Method**, Anonymous or Account. Fill the Login User and Password (It depends on the privacy of the shared folder, ignore if anonymous is chosen).

6.3 Filled the **Path** of the shared folder. (\\210.66.97.246\share in this example)

6.4 Click **Test** button. A test pop up window shows as following:



Test and configure until the test status is **Success**.

6.5 Select the **Shared Folder Method**.

6.6 Select the **Recording Method**.

6.7 Click **Apply** button to save.