



While DHCP Server was enabled , then if you want to make a fixed mapping between the MAC address and the assigned IP address . You may refer to below steps.

1.>Press “DHCP Server” , then press the “Fixed Mapping”



2.>Enable the “MAC Address Control” and select the DHCP clients from the pull list.



3.>Select the “Fixed Mapping ID” and press ”Copy to” button , then DHCP client's IP and MAC address will be copied to the Fixed Mapping Table.

The screenshot shows the 'MAC Address Control' configuration page in the Air Live GW-300R web interface. The page includes a navigation menu with options like 'ADMINISTRATOR'S MAIN MENU', 'Status', 'Wizard', 'Advanced', 'Logout', and 'English'. The main content area is divided into sections for 'MAC Address Control', 'Connection control', and 'Association control'. A 'DHCP clients' dropdown is set to '00-0D-61-27-37-50 : 192.168.1.100 (mychat-f851158b)'. The 'Schedule rule' is set to '(00)Always'. A 'Copy to' button is highlighted in red, and the 'Fixed Mapping ID' dropdown is set to '1'. Below this is a table with columns for ID, MAC Address, IP Address, C, A, and Schedule Rule#.

ID	MAC Address	IP Address	C	A	Schedule Rule#
1	00-0D-61-27-37-50	192.168.1.100	<input type="checkbox"/>	<input type="checkbox"/>	0
2		192.168.1.	<input type="checkbox"/>	<input type="checkbox"/>	0
3		192.168.1.	<input type="checkbox"/>	<input type="checkbox"/>	0
4		192.168.1.	<input type="checkbox"/>	<input type="checkbox"/>	0

4.> Then DHCP Server will reserve the special IP for designated MAC address.